

# **ID TECH MiniMag II Install for WizzForms and VeriScan**



**IDScan.net**

## Installation

1. Download driver from (<https://idscan.net/support/driversfirmware/>)
2. Plug in your scanner and allow Windows to install the basic drivers
3. Unzip your downloaded file (**USBCDC\_Driver\_A.zip**) until you are left with the folder **80066803-004\_USBCDC\_Driver**
4. Open Device Manager on your PC
5. Click on Ports and right-click USB Serial Device
6. Update driver
7. Select Browse my computer for driver software
8. Point it to your previously unzipped folder, then click OK
9. Select Next and Windows should install update the scanner with the required drivers

## Setup with WizzForms and VeriScan

### WizzForms

1. Start WizzForms
2. Right-click on the WizzForms icon located in the System Tray
3. Go to Reader/Scanner #1 and then select ID TECH MiniMag II USB-CDC Reader from the drop down

### VeriScan

1. Start VeriScan
2. Click on the Scanners/Images tab
3. Select ID TECH MiniMag II USB-CDC Reader from one of the available drop down menus at the top left

## Contact

Email: [support@idscan.net](mailto:support@idscan.net)

Phone: 631-380-8121 ext 108