E-Seek M280 Drivers Install



Intro

This short guide will inform you on how to properly install the drivers for the E-Seek M280 scanner.


Getting Started

First thing you'll want to do is download **2 drivers** located on our website here: https://idscan.net/support/driversfirmware/.

Under E-Seek > M280, download the two drivers listed (**Driver download** and **Image driver download**).



Navigate to where your downloaded files are located and right-click the .zip file named M280v2_Driver and select Extract All.



Install


Run the setup file named CDM21228_Setup.exe (Driver download).

Open Device Manager and Look for Other devices > M280V2.



Right-click on M280V2 and select Update driver.

Select Browse my computer for driver software.



Browse to where you previously extracted the M280V2_Driver.zip to and select your appropriate OS from the list.

Your scanner should now be ready to use.

